

# Andriod SDK User Guide

Version 1.3

Vimu Electronic Technology

2025-3-26

<http://www.vimu.top/>

# Update Log

V1.0 (2023.9.20)

Init Versin

V1.1 (2023.11.22)

Add DDS

Add MSO10 Support

V1.4 (2024.7.18)

Add MSO41 Support

V1.3 (2025.3.26)

Add ReScan USB device function

## Catalog

1.	Introduction .....	1
2.	Permission Request .....	1
2.1.	USB Permission .....	1
2.2.	Large Heap Permissions .....	1
3.	UsbDevMng .....	1
3.1.	Creation and initialization .....	1
3.2.	Device status change notification processing .....	1
3.3.	Re-scan the device that has been plugged in .....	2
4.	OscDdsFactory .....	2
5.	Oscillograph .....	2
5.1.	Capture Range Set .....	2
5.2.	Sample .....	3
5.3.	Trigger(hardware trigger) .....	3
5.4.	AC/DC .....	7
5.5.	Capture .....	7
5.6.	Capture Completion Notice .....	8
5.7.	Data Read .....	8
6.	DDS .....	9

## 1. Introduction

The MSO Mixed Signal Oscilloscope is equipped with an Android aar interface, through which the mixed signal oscilloscope can be directly controlled.

This interface can be used on Android systems that support USB Host.

## 2. Permission Request

### 2.1. USB Permission

Add the following information to the file AndroidManifest.xml.

```
<uses-feature
    android:name="android.hardware.usb.host"
    android:required="true" />

<uses-permission android:name="android.hardware.usb.host"/>
<uses-permission android:name="android.permission.HARDWARE_TEST"/>
<uses-permission android:name="android.permission.SYSTEM_ALERT_WINDOW"/>

<intent-filter>
    <action android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED" />
</intent-filter>

<meta-data
    android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED"
    android:resource="@xml/device_filter" />
```

Copy the device\_filter.xml to the res/xml directory.

### 2.2. Large Heap Permissions

Because the capture card supports a maximum storage depth of 32MB, in order to make the app apply for more memory, the following content is added.

```
android:largeHeap="true"
```

## 3. UsbDevMng

UsbDevMng is used to manage device insertion and unplugging detection, and is notified through the UsbDevMng.UsbDevDetectLister interface.

### 3.1. Creation and initialization

```
usbManger = new UsbDevMng(UsbDevDetectLister UsbDevDetectLister);
usbManger.intiDetect(Context context);
```

### 3.2. Device status change notification processing

```
public void UsbDevDetectCallback(UsbDevMng.DEVICE_DETECT_STATE state, boolean
success, BasicUsbDev dev) {
    if (state == UsbDevMng.DEVICE_DETECT_STATE.DEVICE_ADD) {
        //Device Add
    }
    else if (state == UsbDevMng.DEVICE_DETECT_STATE.DEVICE_REMOVE) {
```

```

        // Device Remove
    }
    else if (state == UsbDevMng.DEVICE_DETECT_STATE.NEED_PERMISSION) {
        //no Permissions
    }
    else if (state == UsbDevMng.DEVICE_DETECT_STATE.NEED_RSCAN) {
    }
}

```

### 3.3. Re-scan the device that has been plugged in

In some systems, after authorization, the broadcast information acquisition will fail, and the device needs to be manually rescanned and connected.

**boolean scanDevice(Context context, boolean requestDialog);**

Description: Re-scan the USB device plugged into the system

Input: **context**

**requestDialog** If there is no permission, whether to reapply

Output: **Return value** success or failed

## 4. OscDdsFactory

OscDdsFactory is used to create controls for oscilloscopes, DDS, or other corresponding functions based on BasicUsbDev devices

CreateSbqCardWave creates the control class for the oscilloscope

**BasicSbqUsbCardVer12 CreateSbqCardWave(BasicSbqUsbCardVer12.WaveReceiveLister callback, BasicUsbDev dev)**

Description: Create an oscilloscope's control class.

Input: **BasicSbqUsbCardVer12.WaveReceiveLister** Waveform update notification

**BasicUsbDev** MSO USB device class

Output: **Return value** oscilloscope's control class

CreateDDSWave creates a control class for DDS signal sources

**BasicHsfUsbWaveV12 CreateDDSWave(BasicUsbDev dev)**

Description: Create an dds control class.

Input: **BasicUsbDev** MSO USB device class

Output: **Return value** DDS control class

## 5.Oscillograph

### 5.1. Capture Range Set

Device with a programmable gain amplifier, when the signal acquisition time is less than the AD range,the signal amplification gain amplifier to use more AD digits, improving the quality of signal acquisition. Dll will adjusted the range of settings according to the pre-gain amplifier automatically.

**int SetRange(int channel, double minv, double maxv);**

Description: Set the range of input signal.

Input: **channel** the set channel

**0** channel 1

1 channel 2

**minv** the minimum voltage of the input signal (V)

**maxv** the maximum voltage of the input signal (V)

Output **Return value** 1 Success

0 Failed

Note: The maximum range of the probe collection X1, the maximum voltage oscilloscope can capture. Like MSO20 is[-12000mV,12000mV].

Note: In order to achieve better waveform, you need to set the acquisition range, based on the magnitude of the measured waveform. When necessary, you can dynamically change the acquisition range.

## 5.2. Sample

**int GetSamplesNum ();**

Description: Get the number of samples that the equipment support.

Input: -

Output **Return value** the support sample number

**int GetSamples(int[] sample, int maxnum);**

Description: Get support samples of equipment.

Input: **sample** the array store the support samples of the equipment

**maxnum** the length of the array

Output **Return value** the sample number of array stored

**int SetSample(int sample);**

Description: Set the sample.

Input: **sample** the set sample

Output **Return value** 0 Failed

other value new sample

**int GetSample();**

Description: Get the sample.

Input: -

Output **Return value** sample

## 5.3. Trigger(hardware trigger)

**Trigger Mode**

enum TRIGGER\_MODE {

AUTO(0),

LIANXU(1)

};

**Trigger Style**

enum TRIGGER\_STYLE {

NONE(0), //not trigger

RISE\_EDGE(1), //Rising edge

FALL\_EDGE(2), //Falling edge

```

EDGE(4), //Edge
PULSE_P_MORE(8), //Positive Pulse width(>)
PULSE_P_LESS(16), //Positive Pulse width(<)
PULSE_P(32), //Positive Pulse width(<>)
PULSE_N_MORE(64), //Negative Pulse width(>)
PULSE_N_LESS(128), //Negative Pulse width(<)
PULSE_N(256); //Negative Pulse width(<>)
};

```

#### **TRIGGER\_MODE GetTriggerMode();**

Description: Get the trigger mode.

Input: -

Output **Return value** TRIGGER\_MODE

#### **void SetTriggerMode(TRIGGER\_MODE mode);**

Description: Set the trigger mode.

Input: **mode** TRIGGER\_MODE

Output -

#### **TRIGGER\_STYLE GetTriggerStyle();**

Description: Get the trigger style.

Input: -

Output **Return value** TRIGGER\_STYLE

#### **void SetTriggerStyle(TRIGGER\_STYLE style);**

Description: Set the trigger style.

Input: **style** TRIGGER\_STYLE

Output -

#### **int GetTriggerPulseWidthNsMin();**

Description: Get the min time of pulse width.

Input: -

Output Return min time value of pulse width(ns)

#### **int GetTriggerPulseWidthNsMax();**

Description: Get the max time of pulse width.

Input: -

Output Return max time value of pulse width(ns)

#### **int GetTriggerPulseWidthDownNs();**

Description: Get the down time of pulse width.

Input: -

Output Return down time value of pulse width(ns)

**int GetTriggerPulseWidthUpNs();**

Description: Set the down time of pulse width.

Input: down time value of pulse width(ns)

Output -

**void SetTriggerPulseWidthNs(int down\_ns, int up\_ns);**

Description: Set the up time of pulse width.

Input: **down\_ns**

**up\_ns** up time value of pulse width(ns)

Output -

**TRIGGER\_SOURCE GetTriggerSource();**

Description: Get the trigger source.

Input: -

Output **Return value**

TRIGGER_SOURCE.CH1	0x0000000000000001L	//CH1
TRIGGER_SOURCE.CH2	0x0000000000000002L	//CH2
TRIGGER_SOURCE.D0	0x0000000000010000L	//Logic 0
TRIGGER_SOURCE.D1	0x0000000000020000L	//Logic 1
TRIGGER_SOURCE.D2	0x0000000000040000L	//Logic 2
TRIGGER_SOURCE.D3	0x0000000000080000L	//Logic 3
TRIGGER_SOURCE.D4	0x0000000000100000L	//Logic 4
TRIGGER_SOURCE.D5	0x0000000000200000L	//Logic 5
TRIGGER_SOURCE.D6	0x0000000000400000L	//Logic 6
TRIGGER_SOURCE.D7	0x0000000000800000L	//Logic 7

**void SetTriggerSource(TRIGGER\_SOURCE source);**

Description: Set the trigger source.

Input: <b>source</b>	TRIGGER_SOURCE.CH1	0x0000000000000001L	//CH1
	TRIGGER_SOURCE.CH2	0x0000000000000002L	//CH2
	TRIGGER_SOURCE.D0	0x0000000000010000L	//Logic 0
	TRIGGER_SOURCE.D1	0x0000000000020000L	//Logic 1
	TRIGGER_SOURCE.D2	0x0000000000040000L	//Logic 2
	TRIGGER_SOURCE.D3	0x0000000000080000L	//Logic 3
	TRIGGER_SOURCE.D4	0x0000000000100000L	//Logic 4
	TRIGGER_SOURCE.D5	0x0000000000200000L	//Logic 5
	TRIGGER_SOURCE.D6	0x0000000000400000L	//Logic 6
	TRIGGER_SOURCE.D7	0x0000000000800000L	//Logic 7

Output -

Note: If the logic analyzer and IO are multiplexed (for example, MSO20, MSO21), the corresponding IO needs to be turned on and set to the input state.

**int GetTriggerLevel();**



Description: Get the trigger level.

Input: -

Output **Return value** level (V)

**void SetTriggerLevel(int level);**

Description: Set the trigger level.

Input: level (V)

Output -

**int GetTriggerSenseDiv();**

Description: Get the trigger sense.

Input: -

Output **Return value** Sense (0-1 div)

**void SetTriggerSenseDiv(int sense, double y\_interval\_v);**

Description: Set the trigger sense.

Input: Sense (0-1 div)

Interval(V)

Output -

Note: The sensitivity of sense triggers ranges from 0.1 div to 1.0 div.

y\_interval\_v The oscilloscope software uses a vertical sensitivity setting, which is the voltage value for each slot.

The SDK can be set by dividing the acquisition range by 10, that is,  $(m\_osc\_range\_maxv - m\_osc\_range\_minv)/10.0$ , and the last sensitivity voltage is  $(m\_osc\_range\_maxv - m\_osc\_range\_minv)/10.0*sense$ .

**int GetTriggerFrontPercent ();**

Description: Get the Pre-trigger Percent.

Input: -

Output **Return value** Percent (5-95)

**void SetPreTriggerPercent(int front);**

Description: Set the Pre-trigger Percent.

Input: Percent (5-95)

Output -

**int IsSupportTriggerForce();**

Description: Get the equipment support trigger force or not.

Input: -

**Return value** 1 support

0 not support

**void TriggerForce();**

Description: Force capture once.

Input: -  
Output: -

#### 5.4. AC/DC

**int IsSupportAcDc(int channel);**

Description: Get the device support AC/DC switch or not.

Input: **channel** 0 :channel 1  
1 :channel 2

Output **Return value** 0 : not support AC/DC switch  
1 : support AC/DC switch

**void SetAcDc(int channel, int ac);**

Description: Set the device AC coupling.

Input: **channel** 0 :channel 1  
1 :channel 2  
**ac** 1 : set AC coupling  
0 : set DC coupling

Output -

**int GetAcDc(int channel);**

Description: Get the device AC coupling.

Input: **channel** 0 :channel 1  
1 :channel 2

Output **Return value** 1 : AC coupling  
0 : DC coupling

#### 5.5. Capture

Call capture function to begin collecting data, **length** is the length you want to capture, using K Units, such as length = 10, is 10K 10240 points. For sample rate greater than or equal the length of the depth of the collection is stored, take the minimum **length** and depth of storage;For the sampling rate is less than the memory depth, take the minimum **length** and one second data collection length. **force\_length** can be forced to cancel the limit of only 1 seconds to be collected.

**int Capture(int length, short capture\_channel, byte force\_length);**

Description: Set the capture length and start capture.

Input: **length** capture length(KB)  
**capture\_channel**  
ch1=0x0001 ch2=0x0002 ch3=0x0004 ch4=0x0008 logic=0x0100  
ch1+ch2 0x0003  
ch1+ch2+ch3 0x0007  
ch1+logic 0x0101  
**force\_length** 1: force using the length, no longer limits the max collection 1 seconds

Output **Return value** the real capture length(KB)

When using normal trigger mode (TRIGGER\_MODE\_LIANXU). The collection command was sent, and the data notification that the collection was complete has not been received. Now,

1. Recommended method: You change the trigger mode to `TRIGGER_MODE_AUTO`, wait for the data notification to be collected, and then stop the software.

**DLL\_API int WINAPI AbortCapture();**

Input:

**int GetHardMemoryDepth();**

Input: -

## 5.6.Capture Completion Notice

```
public boolean WaveReceiveCallBack(boolean success, int length){
    if(success) {
        //Update UI
        runOnUiThread(new Runnable() {
            public void run() {
                WaveReceive(length); //UI datas process
            }
        });
    }
    return true;
}
```

Note: The notification callback function cannot access the Android UI data, so you need to use `runOnUiThread` to run the corresponding data processing function of the UI.

## 5.7.Data Read

```
Input:      channel      read channel  0 :channel 1
                                         1 :channel 2
```

**length**      the buffer length

```
Input:      channel      read channel  0 :channel 1
                                                1 :channel 2
```

Output      **Return value**    0 :not out range  
    1 :out range

**double GetVoltageResolution(byte channel);**

Description:    Return the current voltage resolution value

                 One ADC resolution for the voltage value:

                 Full scale is 1000mv

                 the ADC is 8 bits

                 voltage resolution value = 1000mV/256

Input:          **channel**          **read channel**      0:channel 1  
    1:channel 2

Output          **Return value**    voltage resolution value

**int ReadLogicDatas(byte[] buffer, int length);**

Description:    Read the logic data of mso.

Input:

**buffer**              the buffer to store logic datas

**length**            the buffer length

Output          Return value the read length

## 6. DDS

**int GetDepth();**

Description:    Get DDS depth

Input:

Output:      **Return value** depth

**void SetOutMode(int channel\_index, DDS\_OUT\_MODE out\_mode);**

Description:    Set DDS out mode

Input:          **channel\_index**    0 :channel 1  
    1 :channel 2

**out\_mode**        DDS\_OUT\_MODE.CONTINUOUS 0x00  
    DDS\_OUT\_MODE.SWEEP 0x01  
    DDS\_OUT\_MODE.BURST 0x02

Output

**DDS\_OUT\_MODE GetOutMode(int channel\_index);**

Description:    Get DDS out mode

Input:          channel\_index    0 :channel 1  
    1 :channel 2

Output          **mode**                DDS\_OUT\_MODE.CONTINUOUS 0x00  
    DDS\_OUT\_MODE.SWEEP 0x01  
    DDS\_OUT\_MODE.BURST 0x02

**void SetBoxing(int channel\_index, BOXING\_STYLE boxing);**

Description: Set wave style

Input: **channel\_index** 0 :channel 1  
1 :channel 2  
**boxing** W\_SINE = 0x0001,  
W\_SQUARE = 0x0002,  
W\_RAMP = 0x0004,  
W\_PULSE = 0x0008,  
W\_NOISE = 0x0010,  
W\_DC = 0x0020,  
W\_ARB = 0x0040

Output: -

**void UpdateArbBuffer(int channel\_index, short[] arb\_buffer, int arb\_buffer\_length);**

Description: Update arb buffer

Input: **channel\_index** 0 :channel 1  
1 :channel 2  
**arb\_buffer** the dac buffer  
**arb\_buffer\_length** the dac buffer length need equal to the dds depth

Output: -

**void SetFreq (int channel\_index, int freq);**

Description: Set frequency

Input: **channel\_index** 0 :channel 1  
1 :channel 2  
**freq** frequency

Output: -

**void SetDutyCycle(int channel\_index, int cycle);**

Description: Set duty cycle

Input: **channel\_index** 0 :channel 1  
1 :channel 2  
**cycle** duty cycle

Output: -

**int GetCurBoxingAmplitudeMv(BOXING\_STYLE boxing);**

Description: Get DDS amplitude of wave

Input: **boxing** BX\_SINE~BX\_ARB

Output: Return the amplitude(mV) of wave

**void SetAmplitudeMv(int channel\_index, int amplitude);**

Description: Set DDS amplitude(mV)

Input: **channel\_index** 0 :channel 1  
1 :channel 2  
**amplitude** amplitude(mV)

Output:

-

**int GetAmplitudeMv(int channel\_index);**

Description: Get DDS amplitude(mV)

Input: **channel\_index**            0 :channel 1  
                                     1 :channel 2

Output:        return amplitude(mV)

**int GetCurBoxingBiasMvMin(BOXING\_STYLE boxing);**

**int GetCurBoxingBiasMvMax(BOXING\_STYLE boxing);**

Description: Get DDS bias of wave

Input: **boxing**                    BX\_SINE~BX\_ARB

Output:        Return the bias(mV) range of wave

**void SetBiasMv(int channel\_index, int bias);**

Description: Set DDS bias(mV)

Input: **channel\_index**            0 :channel 1  
                                     1 :channel 2

**bias**    bias(mV)

Output:

-

**int GetBiasMv(int channel\_index);**

Description: Get DDS bias(mV)

Input: **channel\_index**            0 :channel 1  
                                     1 :channel 2

Output:        Return the bias(mV) of wave

**void SetSweepStartFreq(int channel\_index, double freq);**

Description: Set DDS sweep start freq

Input: **channel\_index**            0 :channel 1  
                                     1 :channel 2

**freq**

Output:

-

**double GetSweepStartFreq(int channel\_index);**

Description: Get DDS sweep start freq

Input: **channel\_index**            0 :channel 1  
                                     1 :channel 2

Output:        **freq**

**void SetSweepStopFreq(int channel\_index, double freq);**

Description: Set DDS sweep stop freq

Input: **channel\_index**            0 :channel 1  
                                     1 :channel 2

**freq**  
Output: -

**double GetSweepStopFreq(int channel\_index);**

Description: Get dds sweep stop freq

Input: **channel\_index** 0 :channel 1  
1 :channel 2

Output: **freq**

**void SetSweepTime(int channel\_index, long time\_ns);**

Description: Set DDS sweep time

Input: **channel\_index** 0 :channel 1  
1 :channel 2

**time/ns**  
Output: -

**long GetSweepTime(int channel\_index);**

Description: Get DDS sweep time

Input: **channel\_index** 0 :channel 1  
1 :channel 2

Output: **time/ns**

**void SetTriggerSource(int channel\_index, DDS\_TRIGGER\_SOURCE src);**

Description: Set DDS trigger source

Input: **channel\_index** 0 : channel 1  
1: channel 1  
**src** 0: internal 2  
0: INTERNAL  
1: EXTERNAL  
2: MANUAL

Output: -

**int GetTriggerSource(int channel\_index);**

Description: This routines get dds trigger source

Input: **channel\_index** 0: channel 1  
1: channel 2  
Output: **trigger source** 0: INTERNAL  
1: EXTERNAL  
2: MANUAL

**void SetTriggerSourceIo(int channel\_index, int io);**

Description: Set DDS trigger source io

Input: **channel\_index** 0 : channel 1  
1 : channel 2  
**io** 0 : DIO0

.....  
7 : DIO7

Output: -

Note: You need to use the DIO API to set the corresponding DIO to the input/output state

**int GetTriggerSourceIo(int channel\_index);**

Description: Get DDS trigger source io

Input: **channel\_index** 0 : channel 1  
1 : channel 2

Output: **trigger source io** 0 : DIO0

.....  
7 : DIO7

**void SetTriggerSourceEnge(int channel\_index, DDS\_ENGE enge);**

Description: Set DDS trigger source enge

Input: **channel\_index** 0 : channel 1  
1 : channel 2  
**enge** 0 : rising  
1 : falling

Output: -

**int GetTriggerSourceEnge(int channel\_index);**

Description: Get DDS trigger enge

Input: **channel\_index** 0 : channel 1  
1 : channel 2  
Output: **enge** 0 : rising  
1 : falling

**void SetOutputGateEnge(int channel\_index, DDS\_OUTPUT\_ENGE enge);**

Description: Set DDS output gate enge

Input: **channel\_index** 0 : channel 1  
1 : channel 2  
**enge** 0 : close  
1 : rising  
2 : falling

Output: -

**int GetOutputGateEnge(int channel\_index);**

Description: Get DDS output gate enge

Input: **channel\_index** 0 : channel 1  
1 : channel 2  
Output: **enge** 0 : close  
1 : rising  
2 : falling



**void ManualTrigger(int channel\_index);**

Description: Manual trigger DDS

Input:       **channel\_index**       0 : channel 1  
                                  1 : channel 2

Output:       -

**void ChannelStart (int channel\_index);**

Description: Enable DDS output or not

Input:       **channel\_index**       0 : channel 1  
                                  1 : channel 2

Output:       -

**boolean ChannelsStart (int channel\_index);**

Description: Get DDS output enable or not

Input:       -

Output       **Return value** DDS enable or not